EPYX

Presents LUCASFILM GAMES ™

RESCUE ON FRACTALUS!™

for the Tandy® Color Computer 3

GETTING STARTED

o Insert the RESCUE ON FRACTALUS! program disk into the drive, label facing up and oval cutout pointed toward the back of the system.

o Type DOS and press the ENTER key. This will boot up OS-9. If your computer does not recognize the command DOS, refer to Starting RESCUE ON FRACTALUS! from BASIC.

o If you're using an RGB monitor, type R, otherwise type C.

o Press FIRE BUTTON to begin main game sequence.

o Use the joystick to increase/decrease play level (see operator's manual for joystick instructions).

CONTROLS

FIRE BUTTON
Starts the game.

SHIFT ESC
Exit program to OS-9.

CTRL R
Restarts the game from the beginning.

SPACE BAR
Freezes the screen during a mission. Press again to continue.

Note: please refer to the owner's manual for important details regarding the following controls:

A
Air Lock : opens the air lock doors to let the pilot inside.

B
Boosters : fires the booster rockets.

L
Land: puts ship into an auto-matic landing maneuver.

S
Systems : after you land, use key to turn all systems on and off.

< , > .
Decrease/Increase thrust : decreases/increases speed.

> . key also acts as "launch key"

Starting Rescue on Fractalus! from BASIC

If you have a Color Computer with Disk Extended BASIC revision 0, you can type in the following program and use it to start RESCUE ON FRACTALUS!

The copyright message displayed when the computer is turned on will tell you the version and revision number of the BASIC system in your computer. For example if DISK EXTENDED BASIC 1.0 is displayed, the version number is 1 and the revision number is 0.

Using a formatted diskette OTHER THAN your RESCUE ON FRACTALUS! diskette, enter the following program from Disk Extended BASIC.

```
10 REM ******
20 REM * BOOT RESCUE ON
FRACTALUS! FROM BASIC
30 REM ******
40 FOR I=0 TO 70
50 READ A$
60 POKE&H5000+I,VAL("&H"+A$)
70 NEXTI
80 CLS:PRINT"INSERT RESCUE ON
FRACTALUS DISKETTE"
90 PRINT"INTO DRIVE 0 AND PRESS A
KEY"
100 A$=INKEY$:IF A$=" "THEN 100
110 EXEC &H5000
120 DATA 86,22,8E,26,00,8D,0D
130 DATA FC,26,00,10,83,4F,53
140 DATA 26,03,7E,26,02,39,34
150 DATA 20,10,BE,C0,06,A7,22
160 DATA 86,02,A7,A4,6F,21,6F
170 DATA 23,6C,23,AF,24,10,BE
180 DATA C0,06,A6,23,81,13,27
190 DATA 12,AD,9F,C0,04,4D,27
200 DATA 06,6C,23,6C,24,20,E9
210 DATA 7F,FF,40,35,A0,4F,20
220 DATA F8
```